

ELEC / COMP 177 – Fall 2016

Computer Networking

→ Internet Protocol (IP)

Some slides from Kurose and Ross, *Computer Networking*, 5th Edition

Upcoming Schedule

- **Presentation 2 – Security/Privacy**
 - Presentations – **Nov 3rd, Nov 10th, Nov 15th**
 - Upload slides to Canvas by “midnight” on day before presentation

Network Layer – IP

Why not just use Ethernet?

- Most computer systems use Ethernet networking
- Ethernet provides facilities to
 - Locate computers
 - Forward packets directly
 - Prevent loops
 - ...
- What are the drawbacks of Ethernet for global communication?


Ethernet Drawbacks

- Locating computers
 - Do we really want to broadcast across the Internet?
- Preventing loops
 - Do we really want to rebuild an Internet-wide spanning tree whenever the topology changes?
 - Do we really want packets to live forever if loops remain?
- Unreachable computers
 - What happens if the destination is unreachable?
 - I.e., it doesn't exist, is turned off, is broken, ...


The Internet Protocol

- Datagram
 - Each packet is individually routed
 - Packets may be fragmented or duplicated
 - Due to underlying networks
- Connectionless
 - No guarantee of delivery in sequence
- Unreliable
 - No guarantee of delivery
 - No guarantee of integrity of data
- Best effort
 - Only drop packets when necessary
 - No time guarantee for delivery

An IP Datagram




IP Version



- IPv4 or IPv6
 - Also other, uncommon, options

Time-To-Live




- “Hop count” – decrement each hop
- Discard datagrams with zero TTL

IP: Time-to-Live


- Sender sets a TTL value for each datagram
- Each router decrements the TTL
- When the TTL reaches 0
 - The router drops the datagram
 - The router sends an ICMP error (more later) to the sender
- Effectively a “maximum hop count”
- **Why is this useful / necessary?**

Protocol



- What is encapsulated in this IP datagram?
 - 1 = ICMP, 6 = TCP, 17 = UDP, etc...

IP Addresses




- IP address of source and destination

IP encapsulated in Ethernet

Destination MAC Address				
Destination MAC Address		Source MAC Address		
Source MAC Address				
Type (0x0800)		Version	HdrLen	Type of Service
Total Length		Identification		
Flags	Fragment Offset		Time-To-Live	Protocol
Header Checksum		Source IP Address		
Source IP Address		Destination IP Address		
Destination IP Address		Options and Padding		
Options and Padding		Payload		
Payload				
Ethernet CRC				

Routing Between LANs



(1) A (1) transmits to L (2) using IP.
Ethernet frame destination is router

(3) Router uses IP protocol to forward data.
Eth: update src/dst/crc IP: update TTL/checksum

Frame:

EDA (E)	ESA (A)	0x0800	IPDA (2)	IPSA (1)
---------	---------	--------	----------	----------

Frame:

EDA (L)	ESA (G)	0x0800	IPDA (2)	IPSA (1)
---------	---------	--------	----------	----------

(2) Switch forwards frame to router

(4) Switch forwards frame to destination

IP Address Format

IP Addresses


- IP version 4 addresses are 32-bits
 - Version 6 addresses are 128 bits
- Every network interface has at least one IP address
 - A computer might have 2 or more IP addresses
 - A router has many IP addresses
 - These addresses can be assigned statically or dynamically
- IP addresses are always in big-endian byte order (network byte order)
 - True in general for any integer transferred in a packet header from one machine to another
 - E.g., the port number used to identify a TCP connection

IP Address Format

- IPv4 addresses are usually displayed in dotted decimal notation
 - Each byte represented by decimal value
 - Bytes are separated by a period
 - IP address $0x8002C2F2 = 128.2.194.242$
- IP addresses are hierarchical
 - Address is composed of a network ID and a host ID
 - `www.pacific.edu: 138.9.110.12`

IP Address Structure

- IPv4 Address space (*originally*) divided into classes:



- Special IP addresses
 - Loop-back address: 127.0.0.1
 - Unrouted (private) IP addresses:
 - 10.0.0.0 – 10.255.255.255
 - 172.16.0.0 – 172.31.255.255
 - 192.168.0.0 – 192.168.255.255

A Joke




<http://xkcd.com/742/>

Subnetting


- Divide the network within an organization
 - Basically consider one Class B network to be a collection of many smaller networks
 - Size of smaller networks can be selected by the organization (don't have to be Class C sized networks)
- Internet routers don't need to know about subnetting within an organization
 - Just route their traffic to the organization

Subnetting


Company's Class B Network:




Building 1 Network:



Department 4 network in Building 1:



Floor 13 network in Building 6:



Subnetting

- Can recursively subnet addresses down to as fine a granularity as you want
 - Almost...
 - Minimum-sized subnet has 4 addresses
 - Address 00 names the subnet
 - Address 01 and 10 names hosts
 - Address 11 is the broadcast IP address
- Subnet sizes don't have to be the same
 - One building divided by department, one by floor
 - Department/floor subnets not the same size

Subnet Notation

- A.B.C.D/X
 - IP address of the subnet (with 0's in all host ID bits)
 - X = number of bits in the subnet network address
- Examples:
 - 17.0.0.0/8 – Apple's entire class A address space
 - 17.2.3.0/24 – A class C sized subnet in Apple's network
- Alternatively represented by subnet IP and a bit mask (netmask)
 - 17.0.0.0/255.0.0.0
 - 17.2.3.0/255.255.255.0

Subnet Meaning

- Subnets don't have to have physical meaning
 - Although easier to keep track of if they do...
- Good subnet assignment simplifies routing for internal routers
 - All traffic for "building 1" goes through this port
 - All traffic for "department 3" goes through that port
 - ...

Problems

- Address classes were too “rigid”
 - Class C is too small and Class B is too big in many situations
 - Inefficient use of address space
 - Leads to a shortage of addresses
- Small organizations wanted Class B networks
 - In case they grew to more than 255 hosts
 - But there are only about 16,000 Class B network IDs
- Larger organizations wanted many Class C networks
 - Separate network ID for each router link
- Every router in the Internet had to know about every network ID in every organization
 - Leads to large address tables in every router

Classless InterDomain Routing

- CIDR introduced in 1993
 - Meant to provide more flexible routing
 - Eliminate dependences on “class” networks in routing
- “Supernetting”
 - Combine multiple contiguous networks into one larger network
 - Effectively reduces the number of entries needed in each routing table
 - Inverse of subnetting which takes one larger network and breaks it into multiple contiguous smaller networks

CIDR Idea

- Break up IP address space into *prefixes*
 - Same idea as subnets (138.9/16)
- Each prefix has its own routing entry
 - All traffic to Pacific (138.9/16) within the Internet should be routed the same way, regardless of how Pacific subnets its address space


Route Aggregation

- Example: One ISP handles traffic for two corporate networks (129.32/16 and 129.33/16)
- Aggregate route to 129.32/15 for both networks
 - External routers don't care how the ISP breaks up the network addresses internally!
- Only break them apart when necessary for the last (few) hops

What if there are holes?

- Pacific builds a 4th campus
 - 138.9/16 needs to be routed to Pacific
 - 138.9.8/24 needs to be routed to our satellite campus in Hawaii...
- Do we need to break routes up?
 - 138.9.0/20 (.0-.7)
 - 138.9.8/24 (.8)
 - 138.9.9/24 (.9), 138.9.10/24 (.10), 138.9.11/24 (.11)
 - 138.9.12/22 (.12-.15)
 - 138.9.16/20 (.16-.31)
 - 138.9.32/19 (.32-.63)
 - 138.9.64/18 (.64-.127)
 - 138.9.128/17 (.128-.255)

IP Prefixes



- IP address space can be viewed as a number line
 - Each segment represents an aggregated route
 - Segments can overlap
- Look for smallest segment that matches the destination address : **Longest Prefix Match**

Longest Prefix Match

- Allow more specific entries to supersede more general ones
 - 138.9.8/24
 - Route this traffic to Hawaii
 - 138.9/16
 - Route this traffic to Stockton
 - Except for addresses that match a route with a longer prefix (i.e., 138.9.8/24)
- Allows significantly more route aggregation
- Simplifies things if companies move (physically or to another ISP) their block of IP addresses

IP Address Classes

- CIDR makes address classes less important
- With CIDR, routing is based on arbitrary subdivisions of the address space
 - Aggregate routes into largest possible group
 - Use longer prefixes to deal with exceptions
- Routing
 - Routers use longest prefix matching to determine routes
 - No longer deal with exact matches on class network IDs

ARIN WHOIS Database Search

Relevant Links: [ARIN Home Page](#) [ARIN Site Map](#) Training: [Querying ARIN's WHOIS](#)

Search ARIN WHOIS for: 138.9.1.21

Submit

OrgName: University of the Pacific
OrgID: **UNIVER-95**
Address: 3601 Pacific Ave.
City: Stockton
StateProv: CA
PostalCode: 95211
Country: US

NetRange: **138.9.0.0 - 138.9.255.255**
CIDR: 138.9.0.0/16
NetName: **UOP**
NetHandle: **NET-138-9-0-0-1**
Parent: **NET-138-0-0-0-0**
NetType: Direct Assignment
NameServer: NS1.PACIFIC.EDU
NameServer: NS2.PACIFIC.EDU
Comment:
RegDate: 1990-01-17
Updated: 2007-09-07

RAbuseHandle: **DAVEA-ARIN**
RAbuseName: Lundy, Dave A.
RAbusePhone: +1-209-946-3951
RAbuseEmail: dlundy@pacific.edu

RTechHandle: **EES7-ARIN**
RTechName: Escalante, Edgar
RTechPhone: +1-209-946-3190
RTechEmail: eescalante@pacific.edu


OrgTechHandle: **DAVEA-ARIN**
OrgTechName: Lundy, Dave A.
OrgTechPhone: +1-209-946-3951
OrgTechEmail: dlundy@pacific.edu

Router Operation

What's inside a router?




Simplified model of a router



Basic Router Components

- Key Modules
 - Network Interface
 - Packet processing
 - Packet buffering
 - Packet switching
- Processing and buffering can be centralized or decentralized



Packet Processing

- What does a router need to do?
- Driven by protocols
 - Ethernet
 - IP
 - ARP
 - ICMP
 - Transport: TCP, UDP, etc.

On packet arrival...

- Processing
 - Buffer packet?
 - Determine protocol (e.g., IP vs. ARP)
 - Verify checksum, validate the packet, etc.
 - Collect statistics?
- What's next in the "common" (valid IP packet) case?
 - Select egress link

Selecting an Egress Link

- Forwarding table lookup
 - Longest prefix match
 - Determine next hop IP address and egress link
- **What if no match?**
- **Is this sufficient to route the packet to an output queue?**

Prefix	Next Hop	Port
63/8	128.34.12.1	3
128.42/16	128.34.12.1	3
156.3/16	128.36.21.1	2
156.3.224/19	128.36.129.1	1
128.42.96/20	128.37.37.1	4
128.42.128/24	128.36.129.1	1
128.42.160/24	128.36.21.1	2

Updating the Destination Address

- ARP table lookup
 - Exact match on next hop IP address
 - Determine next hop MAC address
- **What if no match?**

IP	MAC
128.34.12.1	0C:FF:63:82:44:01
128.36.21.1	04:32:11:44:82:60
128.36.21.18	10:44:82:82:44:07
128.37.37.37	08:82:82:44:16:32
128.34.12.14	20:33:71:28:15:70
128.36.21.42	14:93:29:22:15:28

Generating ARP Requests

- Broadcast on output port
 - Ask for MAC address of next hop IP address
- Wait for reply
 - **What do you do with the packet?**
 - **How long should you wait? (tradeoffs?)**
- Receive reply
 - Update ARP table
 - Packet continues along forwarding path

Receiving ARP Requests

- Does the IP address match the IP address of the interface that received the ARP request?
 - Another system is trying to determine your MAC address
 - Respond with the appropriate ARP reply on the same interface
- **Should ARP requests be forwarded if they aren't for the router?**

Updating Packets

- Select egress link
- Update MAC address
- **Is it now OK to forward packet to output queue?**

- IP packet header must be modified
 - **What needs to be modified?**
 - **When should it be modified?**

Buffering

- Why do packets need to be buffered?
 - Waiting for access to a resource (lookup table, switch, etc.)
 - Waiting for an ARP reply
 - ...
- What happens when buffers get full?
 - Packets have to be dropped
- How large do buffers need to be?
 - Statistical multiplexing

Error Handling

- ICMP Messages
 - Notify sender of errors
- Common error types
 - Host/network unreachable
 - No ARP response
 - Time exceeded
 - TTL decremented to zero
 - No route to host
 - No entry in routing table

Routing Algorithms

Two Key Network-Layer Functions

■ Forwarding

- Move packets from router's input to appropriate router output
- *Forwarding table*


■ Routing

- Determine path (route) taken by packets from source to destination
- *Routing algorithms*


■ Road trip analogy:

- **Forwarding**: process of getting through single interchange
- **Routing**: process of planning trip from source to destination

Routing versus Forwarding




Forwarding Table Entries




Generating/Updating Routes

- So far, we have assumed forwarding tables are populated statically by an administrator
- In reality, they are dynamically updated
 - Faster reaction to changing network conditions
- **What makes a good route?**
 - Low delay
 - High bandwidth
 - Low link utilization
 - High link stability
 - Low cost
 - (cheaper to use ISP A than ISP B)

Example Network



"Best" Path



Real Networks Are Complicated

- The Internet in 2003

- <http://www.opte.org/maps/>

